


Jeff Terry
Midwest Astroimaging Conference
July 14, 2007

Why Am I Here?









Apache Point 3.5 m

> 3.5 m Run With All Macs. Sloan Moving That Way

Engineers Dig The BSOD

A problem has been detected and Windows has been shut down to prevent damage to your computer.

The problem seems to be caused by the following file: SPCMDCON.SYS

PAGE_FAULT_IN_NONPAGED_AREA

If this is the first time you've seen this Stop error screen, restart your computer. If this screen appears again, follow these steps:

Check to make sure any new hardware or software is properly installed. If this is a new installation, ask your hardware or software manufacturer for any Windows updates you might need.

If problems continue, disable or remove any newly installed hardware or software. Disable BIOS memory options such as caching or shadowing. If you need to use Safe Mode to remove or disable components, restart your computer, press F8 to select Advanced Startup Options, and then select Safe Mode.

Technical information:

*** STOP: 0x00000050 (0xFD3094C2,0x00000001,0xFBFE7617,0x00000000)

*** SPCMDCON.SYS - Address FBFE7617 base at FBFE5000, DateStamp 3d6dd67c

Not Scientists







> IPRO Course

Telescopes





> Mac mini fits perfectly on the tripod tray



- > Minimalist Interface
- > Simplified Feature Set
- Powerful Processing Routines
- > FITS Viewer
- > Camera Control
- > Pretty Cheap, Too

Starlight Express

> MX7C

> MX7

> SXV-MX7

> SXV-MX7C

> SXV-H9

> SXV-H9C

> SXV-M8C


http://www.astrovid.com

http://www.starlight-xpress.co.uk




Collection

- CCD Camera Controller
- Camera:Open Control Window Menu Item




Collection

- Image Name
 - > Autosave M27_001.SX
- Number of Images
- > Exposure Time
 - Milliseconds Best Exposure Control
 - > 300000 msec = 5 minutes
- > Binning
- Image Type
 - > Progressive
 - Interlaced
 - > Focus
- Acquire




Focusing

- Collect an Image
 - > Pick Bright Star
 - > Not Saturated
 - > Set Time < 5 sec
 - > Click On Star to Select
- Select Focus Image Type
 - > Parameters Screen
 - > Acquire



Focusing

- > Optimize
 - > Pick Bright Star
 - > Not Saturated
 - > Set Time < 5 sec
 - Click On Star to Select
- Select Focus Image Type
 - > Minimize HFD
 - > Maximize Intensity
 - > Maximize Contrast
 - > Exception Minimize For
 - > High Magnification Lunar/Planetary
 - > Daytime Images
- Abort When Finished






- > Focusing Is Crucial To Obtaining The Best Images
 - Image Resolution Is Lost When Imaging At An Incorrect Focus Position


Acquire

- After Focusing
- > Select Image Type
 - > Interlaced
 - > Progressive
- > Acquire
- Check Focus Every15 30 MinutesDepending UponTemperature



Color Imaging

iCCD Automatically Color Converts Your Raw Images If You Are Using A Color Camera





- Bias Frames
 - Bias Frames Subtracted
- Dark Frames
 - Dark Frames Subtracted
- > Light Frames
 - Light Frames Divided

Image Calibration


- iCCD Provides Arithmetic Routines For Handling Dark, Light, and Bias Frames
- Processing These Calibration Frames Always Adds Noise To An Image
- > 90% Of The Time Bias and Dark
 Corrections are Unnecessary For The SX
 Cameras
- Light Frames Are Only Needed To Correct For Vignetting Or Dust Particles

Arithmetic




- > Filters: Arithmetic Menu Item
- > Four Tabs
 - > Alignment and Addition
 - > Subtraction
 - > Multiplication/Division
 - > Rotation

Subtraction




- > Hit Populate Image Buttons
- > Select Two Images To Subtract
- Bias Frames I msec
- Dark Frames Equal To Exposure Time

Multiplication / Division



- > Hit Populate Image Buttons
- > Select Two Images
- > Select Operator and Normalization
- Light Frames Equal To ~ 30000 ADU


Alignment / Addition




- > Finally, happy with an image alignment procedure
- > Addition
 - > Average or Sigma Combine

Alignment / Addition

- > Addition
- Include in AverageBox
- > Equivalent
 Scans in
 Image



Histogram



Histogram Allows For Level Adjustment



- Digital Development
 - Filters:Digital Filters:Digital Development
 - > Filters:Digital Filters:DDP No Sharpen
- > Automatic Level Adjustment

DDP



DDP Image Brings Out Regions of Lower Intensity

DDP



DDP Image Brings Out Regions of Lower Intensity



- > The Hot Pixel Killer
 - > Filters:Digital Filters:Hot Pixel Killer
- > Removes Hot Pixels From A Single Frame
 - Recommended on Color Frames From Color Cameras

Deconvolution


- Should Only Be Used On Luminance Frames
 - Do Not Deconvolve Color Frames
- > Less Is More
 - Deconvolution Adds Significant Noise Per Iteration



- > Lucy-Richardson
 - > Better on Deep Sky
- > Van Cittert
 - > Better on Lunar / Planetary
- > Filters:Expert Filters:Deconvolution


Deconvolution


- Number Of Iterations
- > Relaxation Parameter
 - Controls How Fast Dim Regions Converge
- > PSF Width
 - Width of Perfect System
- > Relaxation Function
 - Controls What Is A Dim Region





Deconvolution


- Select Images ButtonPopulates Images
- Pick The Image
- Deconvolve
















Tri - Color Imaging


- Combine L, R, G, B Frames
- > Split RGB Image To L, R, G, and B Frames
 - Create Synthetic Luminance Frame
- > Filters:Color Synthesis:LRGB Operations

Tri - Color Imaging


- Select Images Button Populates The Frames
- Select RGB/L Frames or RGB Frame
- Create or Split Images
- To Create A Synthetic Luminance From RGB Frames
 - > Create an RGB Then Split




Blink



- > The Blink Routine Helps Supernova and Asteroid Hunters
- > Change Images While Blinking



Help



Make the computer do the work

Still To Come

- Autoguiding
 - > SX Guider
 - > Fishcamp Engineering Guider
- > Advanced Deconvolution Routines
- > Improved Alignment Routines Done
- > Easy of Use Improvements




- > Simple
- > No Feature Bloat
- > Most Features Used On Every Image
- > Easy To Create Pretty Pictures
- > Mac Only



- http://www.iccd.us
- http://www.macastroimager.com
- http://www.macastroimaging.com
- > terryj@iit.edu

Remote Observing



- Global Rent A Scope
- http://www.macastroimager.com/GRAS_Desktop.html



- Evaluation
 - > www.skyinsight.net/maic/eval.php
- > Magazine
 - > www.astrophotoinsight.com

